

Training Caffe model for custom object detection.

So, up to now you should have done and have the following:

- a) Ubuntu 16.04 system.
- b) Installed SIMCAM SDK and Toolchain
- c) Installed Opency 3.4 or higher version

Training your own custom object detection model is very easy using SIMCAM SDK, all you need are video files contain desired object. Here is a simple guide how to do it.

Preparing data for training:


- 1. Open SIMCAM SDK folder and copy all your video files into train/data/Images_xmls/videos folder
- 2. Open terminal in train/data/Images_xmls folder and run video2img.py python script:

```
inomjon@inomjon-C-H310M-K-PRO:~/Projects/SIMCAM_SDK_v1.0.0/train/data/Images_xml
s$ python3 video2img.py
```

It will save one frame as an image per second in JPEGImages folder by default. However, there are options; you can change input folder, output folder and number of frames to save.

- 3. Image annotation. You should annotate extracted images manually. We have provided an open source annotation tool named labelImg. That tool provides the object coordinate in xml format as output for further processing. Simple annotations steps are shown below:
 - a) Execute labelImg file, open image dataset folder (in our case JPEGImages folder) by clicking the OpenDir icon on the left pane.
 - b) Image will appear. Click "Change Save Dir" icon and choose Annotations folder as a save folder. Draw rectangle boxes around the objects by clicking the Create RectBox icon and give a label. These boxes are called bounding boxes.
 - c) Repeat second step for the each image that appears. Below image shows an example of an annotated image.





- 4. If you finished all above steps completely, you get bunch of xml files (annotations) inside Annotation folder and images JPEGImages folder.
- 5. Open terminal inside the Images_xmls folder and run create_txt.py python script:

```
inomjon@inomjon-C-H310M-K-PRO:~/Projects/SIMCAM_SDK_v1.0.0/train/data/Images_xml
s$ python create_txt.py
```

This python script will create train.txt, test.txt, trainval.txt and val.txt files in the ImageSets/Main folder

6. Go in data/lmdb_files folder and create your own labelmap.prototxt file, example has exist in the folder; you can change it according to your dataset.

```
item {
  name: "none_of_the_above"
  label: 0
  display_name: "background"
}
item {
  name: "cat"
  label: 1
  display_name: "cat|"
}
```

7. In the terminal run create_list.sh script:



```
inomjon@inomjon-C-H310M-K-PRO:~/Projects/SIMCAM_SDK_v1.0.0/train/data/tm
/home/inomjon/Projects/SIMCAM_SDK_v1.0.0/train/data
./create_list.sh: line 17: [: missing ']'
Create_list.sh: line 17: [: missing ']'
Create_list.sh: line 17: [: missing ']'
Create_list.sh: line 17: [: missing ']'
Create_list.for Images_xmls test...
I0325 15:51:18.579074 12349 get_image_size.cpp:61] A total of 31 images.
I0325 15:51:19.894744 12349 get_image_size.cpp:105] Processed 31 files.
```

It will generate trainval.txt, test_name_size.txt files in the folder

8. Last step is generating lmdb files, lmdb is caffe's data format for training. In the terminal run create data.sh script:

```
pt/movidius/ssd-caffe/build/tools/convert_annoset --anno_type=detection --label_type=xml --label_ma
home/inomjon/Projects/SIMCAM_SDK_v1.0.0/train/data/lmdb_files/labelmap.prototxt --check_label=True
/opt/movidius/ssd-carre/butld/toots/convert_annoset --anno_type=detection --tabet_type=xmt --tabet_map_rite =/home/inomjon/Projects/SIMCAM_SDK_v1.0.0/train/data/lmdb_files/labelmap.prototxt --check_labet=True --min_dim=0 --max_dim=0 --resize_height=0 --resize_width=0 --backend=lmdb --shuffle=False --check_size=False --en code_type=jpg --encoded=True --gray=False /home/inomjon/Projects/SIMCAM_SDK_v1.0.0/train/data/lmdb_files/test.txt /home/inomjon/Projects/SIMCAM_SDK_v1.0.0/train/data/lmdb_files/lmdb/lmdb_files_test_lmdb
10325 16:03:41.646299 12803 convert_annoset.cpp:122] A total of 31 images.
10325 16:03:41.646529 12803 db_lmdb.cpp:35] Opened lmdb /home/inomjon/Projects/SIMCAM_SDK_v1.0.0/train/data/lmdb_files/lmdb/lmdb_files_test_lmdb
10325 16:03:44.710017 12803 convert_annoset.cpp:201] Processed 31 files.
/opt/movidius/ssd-caffe/build/tools/convert_annoset --anno_type=detection --label_type=xml --label_map_file =/home/inomjon/Projects/SIMCAM_SDK_v1.0.0/train/data/lmdb_files/labelmap.prototxt --check_label=True --min_dim=0 --max_dim=0 --resize_height=0 --resize_width=0 --backend=lmdb --shuffle=False --check_size=False --en code_type=jpg --encoded=True --gray=False /home/inomjon/Projects/SIMCAM_SDK_v1.0.0/train/data/lmdb_files/lmdb/lmdb_files/lmdb/lmdb_files_trainval_lmdb
10325 16:03:45.340495 12813 convert_annoset.cpp:122] A total of 171 images.
10325 16:03:45.340721 12813 db_lmdb.cpp:35] Opened lmdb /home/inomjon/Projects/SIMCAM_SDK_v1.0.0/train/data/lmdb_files/trainval_lmdb
10325 16:03:45.340721 12813 db_lmdb.cpp:35] Opened lmdb /home/inomjon/Projects/SIMCAM_SDK_v1.0.0/train/data/lmdb_files/trainval_lmdb
10325 16:04:02.854202 12813 convert_annoset.cpp:201] Processed 171 files.

It will create_trainval_lmdb and_test_lmdb files in the lmdb folder
```

It will create trainval lmdb and test lmdb files in the lmdb folder.

Train model:

So now, you nearly got everything ready to train the Network with the data prepared by yourself. The last thing is, the Network! SIMCAM team provide a robust Network and all necessary scripts for you to train and deploy your own model on the SIMCAM products.

1. Run gen_model.sh script to generate Network:

```
./gen model.sh <num>
```

```
inomjon@inomjon-C-H310M-K-PRO:~/Projects/SIMCAM_SDK_v1.0.0/train$ ./gen_model.sh 2
"num" is number of classes in your dataset including the background
class. It will create prototxts folder and .prototxt files inside the folder
for training, testing and deploying the model
```

2. To start training run train.sh script:

./train.sh



That's all your custom object detection model is started training. We suggest that you should train the model until loss value become below two. You can get a snapshot in 1000 steps. Total training lasts 120000 steps.

After all, you will get **simcam_iter_xxxxx.caffemodel** inside snapshot folder. And **deploy.prototxt** file inside prototxts folder.

To deploy your trained model on SIMCAM products you can follow "Guide of toolchain installation and usage" document.